


yum install epel-release -y

yum grouplist #其中Available Groups代表未安装的分组

```
[root@slavel ~]# yum grouplist
Loaded plugins: fastestmirror
There is no installed groups file.
Maybe run: yum groups mark convert (see man yum)
Loading mirror speeds from cached hostfile
epel/x86_64/metalink
* base: mirror.jdcloud.com
* epel: mirrors.yun-idc.com
* extras: mirrors.aliyun.com
* updates: mirrors.aliyun.com
epel
mysql-connectors-community
(1/3): epel/x86_64/group_gz
(2/3): epel/x86_64/primary_db
(3/3): epel/x86_64/updateinfo
Available Environment Groups:
  Minimal Install
  Compute Node
  Infrastructure Server
  File and Print Server
  Cinnamon Desktop
  MATE Desktop
  Basic Web Server
  Virtualization Host
  Server with GUI
  GNOME Desktop
  KDE Plasma Workspaces
  Development and Creative Workstation
Available Groups:
  Cinnamon
  Compatibility Libraries
  Console Internet Tools
  Development Tools
  Educational Software
  Electronic Lab
  Fedora Packager
  General Purpose Desktop
  Graphical Administration Tools
  Haskell
  Legacy UNIX Compatibility
  MATE
  Milkymist
  Scientific Support
  Security Tools
  Smart Card Support
  System Administration Tools
  System Management
  TurboGears application framework
  Xfce
```



已经有了xfce

如果系统中已安装会提示在Installed Groups中：

Installed Groups:

- Graphical Administration Tools
- Xfce

Available Groups:

- Cinnamon
- Compatibility Libraries
- Console Internet Tools
- Development Tools
- Educational Software
- Electronic Lab
- Fedora Packager
- General Purpose Desktop
- Haskell
- LXQt Desktop
- Legacy UNIX Compatibility
- MATE
- Milkymist
- Scientific Support
- Security Tools

```
yum groupinstall "X Window system"
```

```
yum groupinstall xfce
```

```
systemctl isolate graphical.target
```

```
yum install vnc-server
```

```
cp /lib/systemd/system/vncserver@.service /etc/systemd/system/vncserver@:1.service
```

```
vi /etc/systemd/system/vncserver@:1.service #修改下面信息为自己的
```

```
ExecStart=/sbin/runuser -l <USER> -c "/usr/bin/vncserver %i"
```

```
PIDFile=/home/<USER>/.vnc/%H%i.pid
```

```
# Clean any existing files in /tmp/.X11-unix environment
ExecStartPre=/bin/sh -c '/usr/bin/vncserver -kill %i > /dev/null 2>&1 || :'
ExecStart=/usr/sbin/runuser -l root -c "/usr/bin/vncserver %i"
PIDFile=/root/.vnc/%H%i.pid
ExecStop=/bin/sh -c '/usr/bin/vncserver -kill %i > /dev/null 2>&1 || :'
```

[Install]

这里以root为例，修改后如下：

```
ExecStart=/usr/sbin/runuser -l root -c "/usr/bin/vncserver %i"
```

```
PIDFile=/root/.vnc/%H%i.pid
```

设置vnc密码：

```
vncpasswd
```

```
systemctl daemon-reload
```

```
systemctl enable vncserver@:1.service && systemctl start vncserver@:1.service
```

vi /root/.vnc/xstartup #内容如下

```
#!/bin/sh
```

```
# Uncomment the following two lines for normal desktop:
```

```
unset SESSION_MANAGER
```

```
#exec /etc/X11/xinit/xinitrc
```

```
[ -x /etc/vnc/xstartup ] && exec /etc/vnc/xstartup
```

```
[ -r $HOME/.Xresources ] && xrdp $HOME/.Xresources
```

```
xsetroot -solid grey
```

```
vncconfig -iconic &
```

```
startxfce4 &
```

重启服务：

```
systemctl restart vncserver@:1.service
```

客户端远程连接：


<http://mirror.xrk.org/vnc/VNC-Viewer-6.20.113-Windows.exe>

输入ip:1连接：

192.168.1.100:1



103. [redacted]:1



10 [redacted]